

OpenVMS Enterprise Directory

Installing

Revision/Update Information: Version 5.3

This kit also contains HP Administrator for Enterprise Directory for V2.1.

Checklist:

1. Read the *Read Before Installing* document
2. Check prerequisite software and diskspace
3. Install Version 5.3 of the Directory
Print the release notes and run the IVP during the installation
4. Edit SYSTARTUP_VMS.COM to submit the directory startup procedure during system startup
5. If upgrading or reinstalling, recustomize any customized files, specifically:
The schema files (recompile the schema if you customize it)
DXD\$DSA_STARTUP.NCL
DXD\$TEMPLATE_STARTUP.NCL
DXD\$DSA_STARTUP.COM
DXD\$DSA_SHUTDOWN.NCL
Other files that might have been customized in a previous version are saved during installation. See Saving Files on Reinstallation.
6. Start the Directory

Prerequisite Software

Before you install the OpenVMS Enterprise Directory make sure you have the following installed and working on your system:

- OpenVMS for Alpha V7.3, or later.
- Optionally:
 1. For X.500 protocols over an OSI network, DECnet-Plus V7.3 for OpenVMS Alpha or later. Additionally the OSI Applications Kernel (OSAK) needs to be installed, instructions for which are in the DECnet-Plus for OpenVMS Applications Installation and Advanced Configuration manual. If you have installed DECnet-Plus then you must also install OSAK.
 2. For LDAP or other X.500 protocols that use RFC1006 connections, HP TCP/IP Services for OpenVMS V5.1 or later.
 3. For LDAPv3 over SSL you also require HP SSL Version 1.1 for OpenVMS or later.

Information Required

Before installing, make sure you have the following information:

- The name of the device where the installation media will be loaded.
- The UIC to be assigned to the DXD\$SERVER account.
- The name of the disk where the DXD\$SERVER directory is to be created.
- For clusters, the server node name. See Installing on Clusters.

If this is an upgrade installation, the installation procedure will find the information from the current system.

Disk Space, Resource, and Time Requirements

You need 40000 free blocks on the system device or Alternate Working Device that you use for the installation. If you are installing either the HP AED Windows kit or the HP AED Utility, you need an additional 130000 free blocks on this disk. After installation, the components require disk space permanently on both the system disk and the disk where the DXD\$SERVER directory is to be created. Some components need global pages and sections. These requirements are cumulative.

Component	System Disk space	DXD\$SERVER Disk space	Global Pages	Global Sections
Base (mandatory component)	8000	1000	3200	8
Server	18000	-	-	-
Admin ¹	7000	-	3200	4
API	1000	-	-	-
LUC	5000	-	-	-
HP AED ² Windows kit	-	70000	-	-
HP AED Utility	-	60000	-	-

¹ This is not the HP Administrator for Enterprise Directory; it is the Admin component.

² This is the HP Administrator for Enterprise Directory; it is the Windows GUI for managing the Directory.

Before installing, ensure that the system resources allow for all of the components you install, remembering that the Base component is mandatory.

You are recommended to back up your system disk before you begin the installation. Installation of all components takes approximately 15 minutes.

Release Notes and Read Before Installing Document

Read the release notes before installing the software. Use VMSINSTAL OPTIONS N to print the release notes.

The product documentation includes a *Read Before Installing* document, which you must also read.

Installing the OpenVMS Enterprise Directory

Log in to an account with SETPRV and type:

```
$ @SYS$UPDATE:VMSINSTAL DXDA053 device OPTIONS N
```

The installation procedure displays a menu. Select the components that you want to install, and follow the instructions.

The Base component is mandatory on all systems on which you want to run directory applications. It is installed automatically when you select any other component.

Note that components you do not specify are deinstalled if present. You must specify all components that you want on the system, including any that are already present.

HP Administrator for Enterprise Directory

If you want to use HP Administrator for Enterprise Directory[†] for management of your directory, you should first install the components "hp Administrator for Enterprise Directory—Windows" and "hp Administrator for Enterprise Directory—Utility". When the installation is complete, set DXD\$DIRECTORY to be your default directory, and copy the file [.CAED_WIN32]DIRECTORYADMINISTRATOR.EXE to your PC. This file is an executable program that when run on a PC will install HP Administrator for Enterprise Directory.

You can also check for a later version of the program that can be downloaded directly onto a PC from
http://www.openvms.compaq.com/commercial/edir/edir_mgt_gui_download.html

Handling Errors

If an error occurs during installation, check the prerequisites, and refer to *OpenVMS Enterprise Directory — Problem Solving* for details of installation problems.

Verifying the Installation

To verify the installation, run SYS\$TEST:DXD\$IVP.COM.

Tasks After Installation

Edit SYS\$STARTUP:SYSTARTUP_VMS.COM to include the following command line:

```
$ SUBMIT SYS$STARTUP:DXD$COMMON_STARTUP.COM
```

You also need to run that Directory Service startup file before configuring the product as described in *OpenVMS Enterprise Directory — Management*.

If you are reinstalling or upgrading, then you might have old copies of customized schema files. You need to incorporate your customizations into the newly installed schema files, and recompile the schema before starting the DSA. The *Read Before Installing* document provides further information about upgrading.

[†] See the file ReadMe.txt in the HP Administrator for Enterprise Directory kit for details.

Saving Files on Reinstallation

The installation procedure saves copies of the following files if you reinstall the Directory.

```
SYSSCOMMON:[SYSSSTARTUP]DXD$DSA_STARTUP.NCL
SYSSCOMMON:[SYSSSTARTUP]DXD$DSA_STARTUP.COM
SYSSCOMMON:[SYSSSTARTUP]DXD$DSA_SHUTDOWN.NCL
SYSSCOMMON:[SYSSSTARTUP]DXD$TEMPLATE_STARTUP.NCL
DXD$DIRECTORY:DXD$ACL_TEMPLATE.DXIM
```

Each file is renamed by inserting `_SAV n` into the file name, where n is a number.

If the installation procedure finds schema files, these are moved to a subdirectory called `SAV n` , for example, `DXD$DIRECTORY:[DXD$SERVER.SAV1]`. The procedure only moves schema files that were installed by the Directory product. Any schema files created by the customer are unaffected.

Installing on Clusters

Only one node in a cluster can run the server. The installation prompts you for the server node name, and edits `DXD$LOGICALS_STARTUP.COM` to define a logical based on your answer.

On a cluster that has multiple system disks (including mixed architecture clusters), you must repeat the installation for each system disk. All system disks must run V5.3 of the Directory Service. You must install the same components and specify the same server node during each installation.

The installation registers the `DXIM` command. To make the command available to all cluster nodes, use the following command on each node:

```
$ INSTALL SYS$SHARE:DCLTABLES /REPLACE
```

If you prefer, you can use the `SYSMAN` utility for this task.

No AutoAnswer Support in Installation

AutoAnswer files can only be used on installations that follow the pattern of previous installations. AutoAnswer files created during a first-time installation (that is, installation on a system that had no Directory previously), are not available during an upgrade. AutoAnswer files created during an upgrade will be available at the time of the next upgrade and any subsequent upgrade.

Further Information

OpenVMS Enterprise Directory — Problem Solving contains a list of the files installed on your system, their locations and approximate sizes. The guide also lists errors that you might see during installation and verification and explains what to do if they occur.

© Copyright 2001-2003 Hewlett-Packard Development Company, LP